

ASCII

0	NUL	16	DLE	32	SPC	48	0	64	@	80	P	96	`	112	p
1	SOH	17	DC1	33	!	49	1	65	A	81	Q	97	a	113	q
2	STX	18	DC2	34	"	50	2	66	B	82	R	98	b	114	r
3	ETX	19	DC3	35	#	51	3	67	C	83	S	99	c	115	s
4	EOT	20	DC4	36	\$	52	4	68	D	84	T	100	d	116	t
5	ENQ	21	NAK	37	%	53	5	69	E	85	U	101	e	117	u
6	ACK	22	SYN	38	&	54	6	70	F	86	V	102	f	118	v
7	BEL	23	ETB	39	'	55	7	71	G	87	W	103	g	119	w
8	BS	24	CAN	40	(	56	8	72	H	88	X	104	h	120	x
9	HT	25	EM	41	)	57	9	73	I	89	Y	105	i	121	y
10	LF	26	SUB	42	*	58	:	74	J	90	Z	106	j	122	z
11	VT	27	ESC	43	+	59	;	75	K	91	[	107	k	123	{
12	FF	28	FS	44	,	60	<	76	L	92	\	108	l	124	
13	CR	29	GS	45	-	61	=	77	M	93	]	109	m	125	}
14	SO	30	RS	46	.	62	>	78	N	94	^	110	n	126	~
15	SI	31	US	47	/	63	?	79	O	95	_	111	o	127	DEL

Windows 1250

Znaky č. 0 až 127 jsou shodné s kódem ASCII															
128	€	144		160	NBSP	176	°	177	Ř	208	Đ	224	í	240	ď
129		145	Ž	161	˘	177	±	178	Á	209	Ñ	225	á	241	ń
130	,	146	'	162	˙	178	„	179	Â	210	Ň	226	â	242	ň
131		147	“	163	Ł	179	†	180	Ă	211	Ó	227	ă	243	ó
132	„	148	”	164	ł	180	‘	181	Ä	212	Ô	228	ä	244	ô
133	...	149	•	165	Ą	181	μ	182	Í	213	Õ	229	í	245	õ
134	†	150	—	166	ł	182	¶	183	Ć	214	Ö	230	ö	246	ö
135	‡	151	—	167	§	183	·	184	Ç	215	×	231	ç	247	÷
136		152		168	˘	184	„	185	Č	216	Ř	232	č	248	ř
137	‰	153	™	169	©	185	ą	186	É	217	Ů	233	é	249	ů
138	Š	154	š	170	Ş	186	ş	187	Ę	218	Ú	234	ę	250	ú
139	‹	155	›	171	«	187	»	188	Ě	219	Ů	235	ě	251	ů
140	Ś	156	ś	172	˘	188	ł	189	Ě	220	Ü	236	ë	252	ü
141	Ť	157	ť	173	-	189	˘	190	Í	221	Ý	237	í	253	ý
142	Ž	158	ž	174	®	190	ł	191	Î	222	Ť	238	î	254	ț
143	Ž	159	ž	175	Ž	191	ž	192	Ď	223	ß	239	ď	255	·